


# Installation manual

Daan De Wilde

## Cloning the GitHub repo

1. Start by copying the link to my GitHub repository by pressing the green '<> Code' button. Then copy the given link.



- 2. Clone the repository in your projects folder.
- (c) Microsoft Corporation. Alle rechten voorbehouden.


C:\projects>git clone https://github.com/DeWildeDaan/ResearchProject-MCTS5.git

### **Local setup**

1. Start by unzipping the 'AL-demo-files.zip' folder. Your folder structure should look like this:





- At this point you can open the 'selectannotations.py' script in <u>Visual Studio Code</u>, try and run the script. It should create a new folder named 'Labels' with some .xml files in them.
- 3. Once this works your local setup is complete.



# **Google Colab setup**

- 1. Start by navigating to the Google Colab demo.
- 2. Next you can save a copy of the Google Colab notebook.
- 3. Make sure you enable the Hardware accelerator in: Edit -> Notebook settings





### Installing dependencies

- 1. Once you are connected to a Google Colab runtime with GPU you can install the dependencies and packages in that runtime.
- 2. Run the first cell. This will install MaskAL and all needed dependencies to get this demo running. It will take 5-10 minutes to install everything.

```
#First we clone the MaskAL repo and install all needed dependencies.
!git clone https://github.com/pieterblok/maskal.git
!cd maskal && pip install -e .
!pip install cerberus
!pip install baal
!pip install xmltodict
!pip install matplotlib==3.1.3
```

3. Now, run the second cell. This will get the config files and the data from my GitHub, unzip it and put it all in the right folders.

```
[] #Here we get all needed files I provided in my GitHub repo and put them in the correct folders.
|wget https://github.com/DeWildeDaan/ResearchProject-MCTS5/raw/main/AL-demo-files.zip
|unzip AL-demo-files.zip > /dev/null
|rm AL-demo-files.zip
|mv AL-demo-files maskal/AL-demo-files
|mv maskal/AL-demo-files/config/config_AL.yml maskal/config_AL.yml
|mv maskal/AL-demo-files/config/random.yml maskal/config_random.yml
|rmdir maskal/AL-demo-files/config
```

4. Finally run the third cell. This will import the needed packages for making the plots.

```
[ ] #Some basic imports
import matplotlib.pyplot as plt
import seaborn as sns
import pandas as pd
```

